

GA guide for Windows

Table of Contents

Step 1: Open " This PC " on the desktop

Step 2: Find the location `C:\Windows\System32\drivers\etc` , then click " hosts " file.

Step 3: Choose " Notepad " to open this file


Step 4: Select the location and copy the blue content below, paste it at the end of this file, then click close.

Step 1: Open " [This PC](#) " on the desktop




Step 2: Find the location `C:\Windows\System32\drivers\etc\` , then click "hosts" file.

`C:\Windows\System32\drivers\etc\`



Step 3: Choose " [Notepad](#) " to open this file



Step 4: Select the location and copy the **blue content** below, paste it at the end of this file, then click close.


Europe

8.208.3.231 video1.xjtlu.edu.cn

Southeast Asia

161.117.180.6 video1.xjtlu.edu.cn

```
*C:\Windows\System32\drivers\etc\hosts - Notepad++
文件(F) 编辑(E) 搜索(S) 视图(V) 编码(N) 语言(L) 设置(O) 工具(O) 宏(M) 运行(R) 插件(P) 窗口(W) ?
hosts x hosts x
1 # Copyright (c) 1993-2009 Microsoft Corp.
2 #
3 # This is a sample HOSTS file used by Microsoft TCP/IP for Windows.
4 #
5 # This file contains the mappings of IP addresses to host names. Each
6 # entry should be kept on an individual line. The IP address should
7 # be placed in the first column followed by the corresponding host name.
8 # The IP address and the host name should be separated by at least one
9 # space.
10 #
11 # Additionally, comments (such as these) may be inserted on individual
12 # lines or following the machine name denoted by a '#' symbol.
13 #
14 # For example:
15 #
16 #     102.54.94.97       rhino.acme.com          # source server
17 #     38.25.63.10      x.acme.com              # x client host
18 #
19 # localhost name resolution is handled within DNS itself.
20 #   127.0.0.1          localhost
21 #   ::1               localhost
22 #
23 161.117.180.6 video1.xjtlu.edu.cn
24 #
25 #
26 #
27 #
```



Online URL: <https://knowledgebase.xjtlu.edu.cn/article/ga-guide-for-windows-354.html>